

Garden Princess

Quilt designed by Marinda Stewart. Finished quilt size approximately 51" x 54".

CX3062 Garden Princess- Cream	1 yard
CX1087 Marble- Sienna	3/4 yard
K1167 Krystal- Smoky Blue	1/2 yard
CX1753 Fiesta Texture- Rust	3/8 yard
CX1753 Fiesta Texture- Brown	1/4 yard
Backing	57" x 60"
Batting	57" x 60"
Acrylic ruler, mat and rotary cutter	
100% cotton thread to match	
Basic sewing supplies	

Center Panel Assembly Instructions:

1. From CX3062, cut one 24-1/2" x 42-1/2" panel, with the motif in the center. Put aside the extra fabric from each side of the panel.
2. From CX1753-Brown, cut one 4-12" x 29" strip. Align the left end of the strip with top left corner of the center panel.
3. Pin the 4-1/2" x 29" strip to the top of the panel. You will have extra brown fabric extend past the right edge of the panel. Do not trim this off. Sew the brown strip to the top of the panel stopping 1/4" away from the right edge of the panel.
4. From CX1753-Rust, cut one 4-1/2" x 46" strip. Piece this strip together if necessary.
5. Align the rust strip with the bottom right edge of the panel. Pin the strip in place, leaving the extra tail of the rust fabric at the top of the panel. Sew the strip to the right side of the panel, stopping 1/4" from the top edge of the panel.
6. To miter the upper right corner, fold the panel on the diagonal back sides together. This should line up the borders from the adjacent side (fig. 1).
7. Starting at the sewn seam (represented by the arrow in Figure 1) draw a 45° line out to the edge of the fabric. Sew on the drawn line. Open up the panel and press the mitered seam. Trim away the excess fabric 1/4" away from the sewn seam.




Fig. 3

8. From K1167, cut two 1" x 28-1/2" strips. Sew one strip to the top and bottom of the quilt top. Cut two 1" x 47-1/2" strips. Sew one strip to each side of the quilt top.
9. From CX1087, cut one 2-1/2" x 29-1/2" strip. Sew the strip to the bottom of the panel.
10. From CX1087, cut two 2-1/2" x 49-1/2" strips. Sew each strip onto each side of the panel. Set the panel aside.

Side Pieced Panels Assembly Instructions:

11. From CX3062, cut seven 4-1/2" squares from each of the remaining sides strips for a total of fourteen squares. Maintain the orientation of the panel design on each square as well as the order from top to bottom as you cut them from the strip.
12. Take Template A and cut fourteen pieces from CX1753-Brown. Take Template B and cut fourteen pieces from CX1753-Rust.
13. Align one Brown Template A piece with the top left corner of one 4-1/2" CX3062 square. Sew the brown strip to the top of the square stopping 1/4" from the right side.
14. Align one Rust Template B piece with the lower right corner of the 4-1/2" CX3062 square. Sew the rust strip to the right side of the square stopping 1/4" from the top edge.

Disclaimers

1. This pattern is provided as a courtesy to quilt stores, catalogs and quilters. Michael Miller Fabrics, LLC is not responsible for the accuracy of any kits packaged to accompany this pattern. Please direct any inquiries to the kit maker.
2. Yardage requirements for this pattern may allow for excess yardage to accommodate specific placement of motifs or to allow for any fussy-cutting to achieve the finished quilt design.
3. While every attempt has been made to give accurate measurements, yardage requirements and construction directions, this does not allow for personal variations in measuring, cutting and/or sewing. The enclosed directions were used in the construction of the original quilt.

15. Miter the upper right corner of the block. Repeat with the remaining thirteen blocks.
16. From CX1087-Sienna, cut fourteen 2-1/2" x 5-1/2" strips. Sew one strip to the bottom of each block.
17. Sew seven blocks together to make one side panel make sure to keep the blocks in order from top to bottom as they were cut from the side strips. Repeat to make the other side panel.
18. Sew each side panel to the center panel to make the quilt top.
19. From CX1087-Sienna, cut two 2-1/2" x 49-1/2" strips. Piece them together if needed. Sew one strip to each side of the quilt top. Trim away any excess fabric.
20. To make the Pagoda Roof Panel: from CX1087-Sienna, cut six 2-1/2" x 4-1/2" strips. From K1167, cut five 1" x 2-1/2" strips and two 1-1/2" x 2-1/2" strips.
21. Starting with the 1-1/2" x 2-1/2" K1167 strip, sew it to one 2-1/2" x 4-1/2" CX1087 strip, end to end. Next sew on one 1" x 2-1/2" K1167 strip. Continue to sew the top together alternating the 2-1/2" x 4-1/2" CX1087 Sienna strips with the 2-1/2" x 1" K1167 strips. End with the remaining 1-1/2" x 2-1/2" K1167 strip.
22. From CX1087, cut one of Template C and one of Template C reversed. Sew each to appropriate end of the top pieced strip.
23. Center the finished pieced top on the quilt top and sew in place.
24. Layer backing, batting and the quilt top. Baste and quilt as desired.
25. Bind the bottom of the quilt with CX1087. Bind each side of the quilt with K1167. From the remaining K1167, cut enough bias to make a 2-1/4" x 60" strip. Bind the top edge of the quilt.

Template A
Cut fourteen Brown

Template B
Cut fourteen Rust

Template C
Pagoda Roof
Cut one and
one reversed

