

Kitschy Chickie Kitchen Set

Quilt designed by Marinda Stewart. Finished table runner size approximately 12-1/2" x 50".
Finished placemat size approximately 13-1/2" x 18-1/2" and napkin size approximately 18" square.

Table Runner

Fabric Requirements:

1/2 yard of Jet Brown

3/8 yard of CX3248 Cream

Fat Quarter of CX2879 Maize
Fat Quarter of CX3218 Brown

Fat eighth of CX3155 Cream

Fat eighth of CX2899 Brown
1/6 yard of CX3218 Cream

1/8 yard of CX3195 Brown
1/4 yard of CX3219 Brown

15" x 54" for backing
15" x 54" of batting
Acrylic ruler, mat and rotary cutter
100% cotton threads to match
Basic sewing supplies
Fusible Web

Placemat (makes 2)

Fabric Requirements:

1/2 yard of Jet Brown

1/4 yard of CX3248 Cream

Fat Quarter of CX2879 Maize
Fat eighth of CX3195 Brown
Fat eighth of CX3155 Cream
Fat eighth of CX2899 Brown
1/6 yard of CX3218 Cream
15" x 40" piece for both
placemats backing.
15" x 54" piece of batting for
both placemats.

Napkins (makes 2)

Fabric Requirements:

5/8 yard of CX3218 Cream
5/8 yard of CX3218 Brown

Cutting Instructions:

Cut four 2-1/4" x WOF strips. See Applique instructions.
Cut two 2" x 40-1/2", Six 1" x 10-1/2" strips and four 2" x 9" strips.
Cut two 10-1/2" squares.
Cut eight Template B pieces and eight Template B-R pieces.
Cut one 7-3/4" square, cut it on one diagonal. Cut one 3-1/2" x 7-1/2" strip.
Cut one 3-1/2" x 7-1/2" strip.
Cut one 1-1/2" x WOF strip, four 2-1/2" squares and four Template A pieces.
Cut one 1-1/2" x width of fabric (WOF) strip.
Fussy cut one 3-1/2" Chicken motif and one 3-1/2" square.

Cutting Instructions:

Cut four 2-1/4" x WOF strips. See Applique instructions.
Cut four 2" x 15-1/2" strips and four 2" x 13-1/2" strips.
Cut two 10-1/2" squares.
Cut two 1-1/2" x 22" strip.
Cut two 3-1/2" squares.
Cut two 3-1/2" x 7-1/2" strip.
Cut two 1-1/2" x 22" strips.

Cutting Instructions:

Cut two 18-1/2" squares
Cut two 18-1/2" squares.

Disclaimers

1. This pattern is provided as a courtesy to quilt stores, catalogs and quilters. Michael Miller Fabrics, LLC is not responsible for the accuracy of any kits packaged to accompany this pattern. Please direct any inquiries to the kit maker.
2. Yardage requirements for this pattern may allow for excess yardage to accommodate specific placement of motifs or to allow for any fussy-cutting to achieve the finished quilt design.
3. While every attempt has been made to give accurate measurements, yardage requirements and construction directions, this does not allow for personal variations in measuring, cutting and/or sewing. The enclosed directions were used in the construction of the original quilt.

Applique Instructions:

- 1) Following the manufacturer's instructions, trace two Chickens, two Roosters, six hearts and three set of silverware onto the paper side of the fusible web.
- 2) Roughly cut each shape and press to the back side of the Jet Brown fabric.
- 3) Cut out each shape on the drawn line.
- 4) Press the chicken onto one 10-1/2" CX2879 Maize square. Repeat with the remaining chicken and two roosters and the remaining three 10-1/2" CX2879 Maize square.
- 5) Following the quilt photo as a reference and center two hearts onto one 3-1/2" x 7-1/2" CX3155 strip. Press one heart onto the center of each 3-1/2" CX3155 square. Press one heart in the center each CX3155 triangle. Press each set of silverware onto one 3-1/2" x 7-1/2" strip.
- 6) Finish the raw edges on all the appliques with a decorative stitch such as a buttonhole or satin stitch.

Table Runner Assembly Instructions:

- 7) Sew one Template B and one Template B-R to each side of one Template A piece. Repeat to make four pieced flying geese units.
- 8) Sew one flying goose unit to each side of one 3-1/2" CX3219 Brown square.
- 9) Sew one 2-1/2" CX3218 Cream square to each end of two flying geese units. Sew each flying geese unit to the top and bottom of the 3-1/2" CX3219 Brown square to make the pieced block.
- 10) Sew the double heart applique block from Step 5 to the bottom of the pieced block.
- 11) Sew one 3-1/2" CX3219 Brown Chicken square to the top of one Silverware block. Sew this unit to the right side of the pieced block.
- 12) Sew one 1" x 10-1/2" CX3248 Cream strip to each side of the pieced block and to each side of one Rooster and one chicken block.
- 13) For the checkerboard sashing, sew one 1-1/2" x 22" CX3195 Brown strip lengthwise to one 1-1/2" x 22" CX3218 Cream strip. Repeat with the remaining strips to make two strip sets.
- 14) Cut the strip set into twenty 1-1/2" segments.
- 15) Sew together ten 1-1/2" segments to make one 10-1/2" checkerboard sashing unit. Make two 10-1/2" sashing units total.

- 16) Sew one 10-1/2" checkerboard sashing unit to each side of the pieced block.
- 17) Following the Table Runner photo for placement and sew one Rooster and one Chicken block to each side of the pieced block to make the table runner. Sew one setting triangle to each end of the table runner.
- 18) Sew one 2" x 40-1/2" CX3248 strip to the top and bottom of the table runner. Sew one 2" x 9" CX3248 strip to each side of the setting triangle. Miter corners as needed.
- 19) Layer, quilt and bind as desired.


Placemat Assembly Instructions:

- 1) For the checkerboard sashing, sew one 1-1/2" x 22 CX3195 Brown strip lengthwise to one 1-1/2" x 2 CX3218 Cream strip. Repeat with the remaining strips to make two strip sets.
- 2) Cut the strip set into twenty 1-1/2" segments.
- 3) Sew together ten 1-1/2" segments to make one 10-1/2" checkerboard sashing unit. Make two 10-1/2" sashing units total.
- 4) Sew one 10-1/2" sashing unit to the left side of the remaining two 10-1/2" applique blocks.
- 5) Sew each 3-1/2" Heart block to the top of each Silverware block. Sew this unit to the left side of the checkerboard strip on each placemat.
- 6) Sew one 2" x 15-1/2" CX3248 strip to the top and bottom of each placemat. Sew one 2" x 13-1/2" CX3248 strip to each side of each placemat.
- 7) Layer, quilt and bind as desired.


Napkins Assembly Instructions:

- 1) Place one CX3218 18-1/2" Cream square on top one CX3218 Brown, right sides together. Stitch 1/4" from the edge on all sides. Leave a 4" opening for turning.
- 2) Clip corners and turn the napkins right side out. Slip stitch opening closed. Press.
- 3) Top stitch 1/8" from the outer edge on each placemat to finish.


**Kitschy Chicky Templates
Reversed for Fusible Applique**



**Chicken Template
Trace two**



**Heart Template
Trace Six**




Template A

Grainline


Template B
Reverse for
Template B-R

Grainline


**Kitschy Chicky Templates
Reversed for Fusible Applique**



**Rooster
Cut two**



**Spoon
Cut
three**



Fork Cut three



Knife Cut three