

Dick and Jane Soft Book

Quilt designed by Marinda Stewart. Finished quilt size approximately 8" x 9"

Fabric Requirements:

One complete Panel of DJ3217 White

One fat quarter of each:

CX1065 Garden Pindot-Apple

CX1065 Garden Pindot-Tangerine

CX1065 Garden Pindot-Cherry

CX1065 Garden Pindot-Banana

CX1065 Garden Pindot-Navy

Low-Loft Batting

1-1/4 yards of 3/8" wide ribbon

Twenty-two 1/4" metal eyelets w/
eyelet tool

Pinking Shears

Threads to match

Scissors, Straight Pins, Fabric Pencil

Acrylic Ruler, Mat and Rotary Cutter

Cutting Instructions:

Fussy cut ten 8 1/2" x 9-1/2" pieces, centering a motif in each. Fussy cut ten 4-1/8" squares, centering a small motif in each.

Cut two 9" x 10" pieces from each fat quarter.

Cut four 9" x 10" pieces.

Cut ten 9" x 10" pieces of batting.

Disclaimers

1. This pattern is provided as a courtesy to quilt stores, catalogs and quilters. Michael Miller Fabrics, LLC is not responsible for the accuracy of any kits packaged to accompany this pattern. Please direct any inquiries to the kit maker.
2. Yardage requirements for this pattern may allow for excess yardage to accommodate specific placement of motifs or to allow for any fussy-cutting to achieve the finished quilt design.
3. While every attempt has been made to give accurate measurements, yardage requirements and construction directions, this does not allow for personal variations in measuring, cutting and/or sewing. The enclosed directions were used in the construction of the original quilt.

Assembly Instructions:

1. Layer one large motif, right side up on each piece of batting. Machine quilt around the motifs. Set aside.
2. For the covers, set aside one 9" x 10" navy piece for the back cover. For the front cover, center the 4-1/8" "Dick and Jane" motif from DJ3217 on one 9" x 10" navy piece. The navy piece should be vertical. Place this on top a 9" x 10" piece of batting. Machine applique around the 4-1/8" square.
3. To finish the cover, layer the applied top, right side up, on another CX1065 rectangle. Measure a 7-1/2"W x 8-1/4"H rectangle in the center of the cover rectangle and mark a light line with a fabric pencil. Stitch on this line through all the layers. Stitch a second row 1/4" in from the first sewn line.
4. Take pinking shears and trim the finished page to measure 8"W x 9"H. Set the cover aside.
5. Place one 4 1/8" DJ3217 square in the middle of each remaining 9" x 10" CX1065 rectangle. Machine applique the square in place.
6. To finish the inside pages, place one quilted motif on top of one applied CX1065 rectangle. Using the outside edge of the large quilted motif square as a guide, stitch around all four side. Stitch a second row 1/4" in from the first stitch line all the way around.
7. Take the pinking shears and trim each page to measure 8" W x 9" H. Make nine pages total.
8. To finish the back cover, quilt the last motif to the remaining CX1065 navy square that was set aside for the back cover.
9. Following the manufacturer's instructions attach two eyelets to the left side of each page 1/2" from the left edge and 2" in from the top and bottom edge.
10. Cut the ribbon into two equal pieces. Thread the ribbon through the eyelets at the top and bottom of each page. Start with the "Dick and Jane" cover and ending with the back cover. Arrange the interior pages as desired.
11. Tie the ribbon into a knot on the front cover. Use the remaining ribbon ends to make a bow. Trim away any excess ribbon.